

# Mastery1-06-Archived-Patterned-Paper-Anchor-manual



## Digital Scrapbooking Mastery, No. 1 Archiving Lesson 6: Patterned Paper Anchor Manual © 2019 Jen White


Photoshop Elements

- Begin in Expert Mode of Photoshop Elements.
- Open the scrapbook page (File > Open) that you ended with in Lesson 6.
- In the Layers panel, the Patterned Paper Anchor group should be the active group.
- Right click (Mac: Ctrl click) on that group and choose Duplicate Group.
- In the dialog box, set the Destination Document to New and click OK.
- In the Layers panel of the new document, Right click (Mac: Ctrl click) on the group and choose Ungroup Layers.
- Click and drag the Effect icon to the Trash icon.

Straighten the Mask

- In the Menu Bar, choose View > Rulers.
- On the document, click and drag out a guide from the Horizontal Ruler so that it's just above the top of the paper piece.

- Get the Zoom tool.
- On the document, click several times to zoom into the top area of the paper piece.
- Press Ctrl T (Mac: Cmd T) to get the Transform options.
- On the document, hold down the Alt key (Mac: Opt key) and click on the topmost corner of the paper.
- In the Tool Options, click and drag in a circular motion on the Angle indicator until the top of the paper is level with the guide.



- Click the checkmark to commit.
- Get the Move tool.
- On the document, click and drag the guide back into the Horizontal Ruler.
- Press Ctrl 0 (Mac: Cmd 0) to zoom out.

#### Remove the Shadow, Crop, and Save

- In the Layers panel, click on the arrow of the Pattern Paper Anchor group to twirl it open.
- Click and drag the Effects icon of the shape layer to the Trash icon.
- Right click (Mac: Ctrl click) on the Pattern Paper Anchor group and choose Ungroup Layers.
- Holding down the Ctrl key (Mac: Cmd key), click on the thumbnail of the shape layer to get a selection outline.
- In the Menu Bar, choose Image > Crop.
- Press Ctrl D (Mac: Cmd D) to deselect.
- Save the document (File > Save As) as a layered PSD file named Patterned Paper Anchor in an easy to find location.

#### Use the Anchor on a New Project

- Open the Pattered Paper Anchor archived file.
- In the Layers panel, activate all the layers.
- On the document, click and drag the anchor to a new document.

## Change the Anchor Color

- In the Layers panel, click and drag the simplified layer to the Trash icon.
- Click on the Visibility icon of the grid paper group to reveal it. Your entire document will now be filled with the patterned paper.
- Click on the arrow to twirl open the grid paper group.
- Click on the color chip of the Color Fill layer to open the Color Picker. Choose a color and click OK.
- Click on the arrow to twirl shut the grid paper group.
- Press Ctrl J (Mac: Cmd J) to duplicate the grid paper group.
- Click on the Visibility icon of the duplicate grid paper group to hide it.
- Click on the visible grid paper group to activate it.
- In the Menu Bar, choose Layer > Simplify Layer.
- Choose Layer > Create Clipping Mask.

## Adobe Photoshop

- Begin in Adobe Photoshop.
- Open the scrapbook page (File > Open) that you ended with in Lesson 6.
- In the Layers panel, the Patterned Paper Anchor group should be the active group.
- Right click (Mac: Ctrl click) on that group and choose Duplicate Group.
- In the dialog box, set the Destination Document to New and click OK.

## Straighten the Mask

- In the Menu Bar, choose View > Rulers.
- On the document, click and drag out a guide from the Horizontal Ruler until it snaps to the top corner of the anchor.
- Holding down the letter Z, click several time on the top of the anchor to zoom in until you can clearly see the top of the paper.
- Press Ctrl T (Mac: Cmd T) to get the Transform options.
- On the document, hold down the Alt key (Mac: Opt key) and click on the topmost corner of the paper.
- In the Tool Options, click and scrub on the Angle icon to rotate the paper until it aligns with the guide. Click the checkmark to commit.
- Get the Move tool.
- On the document, click and drag the guide back into the horizontal ruler.
- Press Ctrl 0 (Mac: Cmd 0) to zoom out.
- On the document, click and drag the guide back up into the horizontal ruler.

## Remove the Shadow, Crop, and Save

- In the Layers panel, open the Pattern Paper Anchor group.
- Click and drag the Effects icon to the Trash icon.
- Right click (Mac: Ctrl click) on the group and choose Ungroup Layers.
- Holding down the Ctrl key (Mac: Cmd key), click on the thumbnail of the shape layer to

get a selection outline.

- In the Menu Bar, choose Image > Crop.
- Press Ctrl D (Mac: Cmd D) to deselect.
- In the Layers panel, click on the shape layer to activate it.
- Save the document (File > Save As) as a layered PSD document with a unique name in an easy to find location.

#### Use the Anchor on a New Project

- Open the Pattered Paper Anchor archived file.
- In the Layers panel, activate all the layers.
- On the document, click and drag the anchor to a new document.

#### Change the Anchor Color

- In the Layers panel, double click on the thumbnail of the grid paper layer to open a smart document (PSB document).
- Click on the arrow to twirl open the grid paper group.
- Double click on the color chip of the Color Fill layer to open the Color Picker. Choose a color and click OK.
- Press Ctrl S (Mac: Cmd S) to save the PSB document. The patterned paper anchor document should now be updated.

#### Change the Anchor Pattern

- In the Layers panel, double click on the thumbnail of the grid paper layer to open a smart document (PSB document).
- In the Layers panel, click on the smart object icon of the pattern fill layer to open another smart document.
- Double click on the thumbnail of the pattern fill layer to open the Pattern Fill dialog box.
- In the Pattern Fill dialog box, change the Scale and click OK.
- Press Ctrl S (Mac: Cmd S) to save the PSB document. The patterned paper anchor document should now be updated.